

## Driver Installation

### M-Bus Mini-Master

Signal-converter



# 1 General

This document describes how to install the M-Bus Mini-Master - driver on Microsoft® Windows® 2000/XP/2003/Vista/2008/7 (32- und 64-bit) systems.

## 2 Table of contents

1	General .....	2
2	Table of contents.....	2
3	USB driver installation.....	2
4	How to change virtual COM port number.....	3


## 3 USB driver installation

Please install the USB driver prior to connecting the M-Bus Mini Master to the computer.


- To install the driver, simply double click the setup file located at [www.aquametro.com](http://www.aquametro.com) homepage:  
„**M-Bus Mini Master\_Setup.exe**“
- Once installed, you can connect the USB Interface to the computer.
- When connected, two new entries are added in Windows Device Manager:
  - New USB device:  
Universal Serial Bus controllers: „**USB Serial Converter**“
  - New virtual COM port:  
Ports (COM & LPT): „**USB Serial Port (COMx)**“
- The M-Bus Mini Master interface is now ready to use.

## 4 How to change virtual COM port number

- Close all applications which are accessing the COM port.
- To change the COM port number of your USB interface, go to Windows Control Panel  
**Start | Control Panel | System and Maintenance | System | Device Manager**
  - Double click “USB Serial Port (COMx)”



- Navigate to Port settings -> Advanced...



- Select COM port and click OK and close Windows Control Panel.
- Your computer will keep this setting, even when connecting the USB Interface to a different USB port.

